



Installing PATLink with custom password for SQL2012 Express

Proceed to step 9 if PATLink PRO was never installed before on the computer where you will use custom password.


1. From Control Panel run **Programs and Features**
2. Uninstall **SQL2005** or **SQL2012** instance **METREL**




3. Click "OK"




4. Select "METREL" and click "Next"




5. Click "Select All" than click "Next"




6. Click "Next"



7. Click "Remove"




8. Click "Close"




9. Download PATLink PRO from link:

[>>>Download PATLink PRO v1.9.33](#)


10. Extract downloaded file.




11. Run extracted file as Administrator




12. Select directory to extract installation files.




13. From installation files run **Main Folder/SqlExpress/SQLExpr2012_x64_ENU.exe**




14. Select **"New SQL Server stand-alone installation or add features to an existing installation"**.




15. Click **“Next”**




16. Select **“Perform a new installation of SQL Server 2012”** and click **“Next”**.




17. Select **"I accept the license terms"** and click **"Next"**.




18. Click **"Select All"** and **"Next"**.




19. Select **“Named instance”** and enter name **“METREL”**. Click **“NEXT”**.




20. For **SQL Server Database Engine** select **“<<<Browse..>>”** and click **“Advanced”**.




21. Click **"Find Now"**, select **"SYSTEM"** and click **"OK"**.



22. Click **"OK"**.




23. Click "Next".




24. Select "Mixed Mode" and enter **Metrel@1234**. Click "Next".


See password requirements from link: [SQL Strong Password Requirement](#)



25. Click **“Next”**.



26. Click **“Close”**.



27. Install PCSW **PATLink PRO** by running **setup.exe**.

Name	Date modified	Type	Size
dotnetfx	20/05/2015 15:22	File folder	
MDAC28	20/05/2015 15:22	File folder	
SqlExpress	20/05/2015 15:23	File folder	
WindowsInstaller3_1	20/05/2015 15:22	File folder	
deploy	20/05/2015 15:25	Windows Installer ...	68,133 KB
setup	20/05/2015 15:25	Application	2,464 KB

28. Enter **Metrel@1234** when required.

Password requirement

Enter the password needed for database connection, please

Password
.....

Confirm password
.....

OK Skip